

CanOEs - CAN Communication GUI

User Manual

Version: 1.0

Date: December 2025

Author: Dariusz Piskorowski

Table of Contents

1. [Introduction](#)
2. [Requirements](#)
3. [Getting Started](#)
4. [Main Interface Overview](#)
5. [Connection Panel](#)
6. [Send Panel](#)
7. [Received Messages Panel](#)
8. [Tabs Overview](#)
9. [Main Tab](#)
10. [Filters Tab](#)
11. [Periodic Tab](#)
12. [Timing Tab](#)
13. [History Tab](#)
14. [Predefined Tab](#)
15. [Grouped Tab](#)
16. [Features](#)
17. [Theme Toggle](#)
18. [Export Logs](#)
19. [Message Coloring](#)
20. [ASCII Preview](#)
21. [ID Comments](#)
22. [How-To Guides](#)
23. [Troubleshooting](#)

1. Introduction

CanOEs (CAN Open Environment Software) is a graphical user interface for CAN and CAN FD communication using Vector VN1640A hardware. It provides an intuitive way to send, receive, filter, and analyze CAN messages.

Key Features:

- CAN Classic (up to 8 bytes) and CAN FD (up to 64 bytes) support
 - Standard (11-bit) and Extended (29-bit) ID support
 - Message filtering by ID, range, or mask
 - Periodic message transmission
 - Message history and predefined messages
 - Dark/Light theme support
 - Export logs to TXT file
-

2. Requirements

Hardware:

- Vector VN1640A CAN interface (or compatible VN16xx device)

Software:

- Windows operating system
 - Vector XL Driver Library (vxlapi64.dll)
 - Python 3.8 or higher
 - Required Python packages:
 - `tkinter` (usually included with Python)
-


3. Getting Started

1. **Connect Hardware:** Connect your Vector VN1640A to the computer via USB
2. **Install Drivers:** Ensure Vector drivers are installed
3. **Run Application:** Execute `python can_gui.py`

- 4. **Select Channel:** Choose the CAN channel (1-4)
- 5. **Select Mode:** Choose CAN or CAN FD mode
- 6. **Connect:** Click the "Connect" button

4. Main Interface Overview

The application window is divided into several sections:



5. Connection Panel

Located at the top of the window, this panel controls the connection to the CAN hardware.

Controls:

| Control | Description |
|-------------|--|
| Channel | Dropdown to select CAN channel (1, 2, 3, or 4). Corresponds to physical channels on VN1640A. |
| Baudrate | CAN bus speed selection: 125k, 250k, 500k, 1M bit/s |
| FD Baudrate | Data phase baudrate for CAN FD: 1M, 2M, 4M, 5M, 8M bit/s |

| Control | Description |
|------------------------|---|
| CAN FD Checkbox | Enable CAN FD mode (allows up to 64 bytes per message) |
| Connect Button | Establishes connection to selected channel. Changes to "Disconnect" when connected. |

Connection Status:

- **Disconnected:** Gray status, "Connect" button visible
- **Connected:** Green status, "Disconnect" button visible
- **Error:** Red status with error message

6. Send Panel

This panel allows you to compose and send CAN messages.

Controls:

| Control | Description |
|---------------------|--|
| ID (hex) | Message ID in hexadecimal (e.g., <code>123</code> , <code>7DF</code> , <code>18DA00F1</code>) |
| Extended ID | Checkbox - enable for 29-bit extended CAN ID |
| FD | Checkbox - send as CAN FD frame (allows more than 8 bytes) |
| BRS | Checkbox - Bit Rate Switch (faster data phase in CAN FD) |
| Data (hex) | Message payload in hexadecimal, space-separated (e.g., <code>01 02 03 04</code>) |
| Byte Counter | Shows current/maximum bytes (e.g., <code>8/8 bytes</code> or <code>8/64 bytes</code> for FD) |
| Pad 00 | Button - fills remaining bytes with zeros (to 8 for CAN, 64 for CAN FD) |
| Send | Button - transmits the message |

Data Length Validation:

- **CAN Classic:** Maximum 8 bytes

- **CAN FD**: Maximum 64 bytes
- Counter turns **red** if data exceeds the limit
- Message will not be sent if data is too long

Examples:

Standard CAN message: - ID: 123 - Extended ID: ☐ (unchecked) - FD: ☐ (unchecked) - Data: 01 02 03 04 05 06 07 08


CAN FD message with BRS: - ID: 456 - Extended ID: ☐ (unchecked) - FD: ☒ (checked) - BRS: ☒ (checked) - Data: 01 02 03 → Click "Pad 00" → 01 02 03 00 00 00 ... 00 (64 bytes)

Extended ID message: - ID: 18DA00F1 - Extended ID: ☒ (checked) - Data: 02 10 01

7. Received Messages Panel

Located in the Main tab, this panel displays all received and transmitted CAN messages.

Toolbar Buttons:

| Button | Description |
|---|---|
| ► Start /  Stop | Start or stop receiving messages |
| Clear | Clear all messages from the list |
| Export TXT | Save message log to a text file |
| Auto-scroll | Checkbox - automatically scroll to newest message |
| Show Time | Checkbox - display timestamp column |
| Show ASCII | Checkbox - display ASCII representation of data |
| Color Messages | Checkbox - enable/disable color coding of messages (TX=green, RX=blue, DIAG=orange) |
| Edit Comments | Open dialog to add/edit comments for message IDs |

Message List Columns:

| Column | Description |
|---------|--|
| Time | Timestamp when message was sent/received |
| Dir | Direction: TX (transmitted) or RX (received) |
| ID | Message ID in hexadecimal |
| DLC | Data Length Code (number of data bytes) |
| Data | Message payload in hexadecimal |
| ASCII | ASCII representation of data (if enabled) |
| Flags | Message flags: EXT (extended), FD, BRS |
| Comment | User-defined comment for this ID |

Message Colors:

| Color | Meaning |
|--------|---|
| Green | TX - Transmitted messages |
| Blue | RX - Received messages |
| Orange | DIAG - Diagnostic messages (known diagnostic IDs) |
| Red | ERR - Error frames |

8. Tabs Overview

8.1 Main Tab

The primary workspace containing: - Received Messages panel with message list - Real-time message display - Message filtering based on active filters

8.2 Filters Tab

Create and manage message filters to show or hide specific CAN IDs.

Filter Types:

| Type | Description | Example |
|--------|--------------------------|---|
| Single | Match exact ID | ID = 0x123 |
| Range | Match ID within range | From 0x100 to 0x1FF |
| Mask | Match IDs using bit mask | Base 0x700 , Mask 0x7F0 matches 0x700-0x70F |

Filter Controls:

| Control | Description |
|--------------------------|--|
| Filter Name | User-friendly name for the filter |
| Filter Type | Single, Range, or Mask |
| Accept/Reject | Accept = show matching, Reject = hide matching |
| Enabled | Checkbox to enable/disable filter |
| Add Filter | Create new filter |
| Remove Selected | Delete selected filter |
| Enable All / Disable All | Batch enable/disable all filters |

8.3 Periodic Tab

Configure messages to be sent automatically at regular intervals.

Periodic Message Settings:

| Setting | Description |
|----------|--|
| ID | Message ID (hex) |
| Data | Message payload (hex) |
| Interval | Time between sends in milliseconds |
| Count | Number of times to send (0 = infinite) |

| Setting | Description |
|-----------------|---------------|
| Extended/FD/BRS | Message flags |

Controls:

| Button | Description |
|-----------|-------------------------------------|
| Add | Add new periodic message |
| Remove | Remove selected message |
| Start All | Start all enabled periodic messages |
| Stop All | Stop all periodic messages |

8.4 Timing Tab

Configure timing parameters for message transmission.

Settings:

| Setting | Description |
|---------------|---|
| Min Frame Gap | Minimum time (ms) between consecutive transmissions |
| TX Timeout | Timeout for transmission confirmation |

8.5 History Tab

View and resend previously transmitted messages.

Features:

- Automatically records all sent messages
- Double-click or select + "Resend" to retransmit
- "Load" button copies message back to Send panel for editing
- "Clear History" removes all history entries

Columns:

| Column | Description |
|--------|----------------------------------|
| Time | When message was originally sent |
| ID | Message ID |
| Data | Message payload |
| Flags | EXT, FD, BRS flags |

8.6 Predefined Tab

Store frequently used messages for quick access.

Default Predefined Messages:

- **Diag 0x744** - 02 10 01 (Diagnostic session)
- **Diag 0x744 Extended** - 02 10 03 (Extended session)
- **OBD Engine RPM** - 0x7DF : 02 01 0C (Request engine RPM)
- **OBD Vehicle Speed** - 0x7DF : 02 01 0D (Request vehicle speed)
- **OBD Coolant Temp** - 0x7DF : 02 01 05 (Request coolant temperature)
- **Tester Present** - 0x7DF : 02 3E 00 (Keep session alive)

Controls:

| Button | Description |
|-------------|---|
| Send | Transmit selected predefined message |
| Add Current | Save current Send panel content as predefined |
| Remove | Delete selected predefined message |

8.7 Grouped Tab

View message statistics grouped by CAN ID.

Columns:

| Column | Description |
|-----------|----------------------------------|
| ID | Unique message ID |
| Count | Number of times this ID was seen |
| Last Data | Most recent payload for this ID |
| Last Time | Timestamp of most recent message |
| Comment | User-defined comment |

Controls:

| Button | Description |
|---------|--------------------------------------|
| Refresh | Update grouped view with latest data |
| Clear | Reset all grouped statistics |

9. Features

9.1 Theme Toggle

Click "**Toggle Theme**" button (top-left) to switch between: - **Light Theme**: White background, dark text - **Dark Theme**: Dark background, light text (easier on eyes)

9.2 Export Logs

1. Click "**Export TXT**" in the toolbar
2. Choose save location and filename
3. File contains all messages in human-readable format: ``` CanOEs - Message Log Exported:
2025-12-05 14:30:00 =====

12:00:01.123 TX 0x123 8 01 02 03 04 05 06 07 08

12:00:01.456 RX 0x456 4 11 22 33 44 ."3D Response ```

9.3 Message Coloring






Messages can be **automatically** color-coded based on their type. This feature is **enabled by default** but can be toggled on/off.

How to enable/disable coloring:

1. In the toolbar above the message list, find "**Color Messages**" checkbox
2. ☒ **Checked** = Colors are applied to messages
3. ☐ **Unchecked** = All messages displayed in default color (black/white depending on theme)

How it works (when enabled):

- Colors are assigned automatically when messages appear in the list
- No additional configuration needed - it just works!
- Repeated messages without data changes will gradually fade (become grayed out)
- Messages with changing data stay in full color

| Color | Type | When Applied |
|---|-------|---|
|  Green | TX | Any message you transmit |
|  Blue | RX | Any message received from the bus |
|  Orange | DIAG | Messages with diagnostic IDs (0x7DF, 0x7E0, 0x7E8, 0x744, 0x74C, 0x700-0x703) |
|  Red | ERR | Error frames |
|  Gray | STALE | Repeated messages with unchanged data (after 5+ repetitions) |

Visual Priority:

1. Error frames are always red
2. Diagnostic IDs override TX/RX color (shown in orange)
3. Stale/repeated messages fade to gray regardless of type

When to disable coloring:

- When you need maximum readability in certain lighting conditions
- When preparing screenshots for documentation
- When you prefer a cleaner, monochrome look

9.4 ASCII Preview

Enable "**Show ASCII**" checkbox to see ASCII representation of data bytes: - Printable characters (32-126) shown as-is - Non-printable characters shown as `.`

Example: - Data: `48 45 4C 4C 4F 00 01 02` - ASCII: `HELLO...`

9.5 ID Comments

Add custom comments to CAN IDs for documentation:

1. Click "**Edit Comments**" button
2. In dialog:
3. Enter ID (hex): `744`
4. Enter Comment: `ECU Diagnostic Request`
5. Click "**Add/Update**"
6. Comments appear in the message list and grouped view

Default Comments:

| ID | Comment |
|-------|---------------------|
| 0x7DF | OBD-II Broadcast |
| 0x7E0 | OBD-II ECU Request |
| 0x7E8 | OBD-II ECU Response |
| 0x744 | Diagnostic Request |
| 0x74C | Diagnostic Response |

10. How-To Guides

This section provides step-by-step instructions for common tasks.

10.1 How to Connect to CAN Bus

Goal: Establish connection to your CAN network

Steps: 1. Plug Vector VN1640A into USB port 2. Wait for Windows to recognize the device 3. Launch CanOE's application 4. In **Connection Panel** (top of window): - Select **Channel**: Usually

1 (check your physical connection) - Select **Baudrate**: Must match your CAN network (common: 500k) - Check **CAN FD** if your network uses CAN FD - If CAN FD, select **FD Baudrate** (common: 2M) 5. Click **Connect** button 6. Status bar should show "Connected" in green

Troubleshooting: - If "Channel not found" → check USB connection - If no messages appear → verify baudrate matches other devices

10.2 How to Send a CAN Message

Goal: Transmit a single CAN message

Steps: 1. Ensure you are connected (see 10.1) 2. In **Send Panel**: - Enter **ID** in hex (e.g., 123 or 7DF) - Check **Extended ID** if using 29-bit ID - Check **FD** for CAN FD message (more than 8 bytes) - Check **BRS** for faster data rate (only with FD) - Enter **Data** in hex with spaces (e.g., 01 02 03 04) 3. Click **Send** button

Example - Standard OBD-II request: - ID: 7DF - Extended ID: ☐ - FD: ☐ - Data: 02 01 0C (request engine RPM)

Example - CAN FD diagnostic: - ID: 744 - Extended ID: ☐ - FD: ☒ - BRS: ☒ - Data: 02 10 01 → Click **Pad 00** → auto-fills to 64 bytes

10.3 How to Filter Messages

Goal: Show only specific CAN IDs

Scenario: You only want to see diagnostic responses (0x74C)

Steps: 1. Go to **Filters** tab 2. Enter filter details: - **Filter Name:** Diagnostic Response - **Filter Type:** Single - **Single ID:** 74C - **Accept/Reject:** Accept (show matching) 3. Click **Add Filter** 4. Ensure **Enabled** checkbox is checked 5. Return to **Main** tab - only matching messages will appear

Scenario: Hide all messages in range 0x100-0x1FF

Steps: 1. Go to **Filters** tab 2. Enter filter details: - **Filter Name:** Hide low IDs - **Filter Type:** Range - **From:** 100 - **To:** 1FF - **Accept/Reject:** Reject (hide matching) 3. Click **Add Filter**

10.4 How to Set Up Periodic Messages

Goal: Send a message automatically every X milliseconds

Scenario: Send "Tester Present" every 2 seconds to keep session alive

Steps: 1. Go to **Periodic** tab 2. Enter message details: - **ID:** 7DF - **Data:** 02 3E 00 - **Interval (ms):** 2000 (2 seconds) - **Count:** 0 (infinite, or enter number for limited sends) 3. Click **Add** 4. Click **Start All** to begin transmission 5. Watch the Main tab - message appears every 2 seconds 6. Click **Stop All** when finished

10.5 How to Use Message History

Goal: Resend a message you sent earlier

Steps: 1. Send some messages normally 2. Go to **History** tab 3. You'll see all previously sent messages with timestamps 4. To resend exact same message: - Select the message - Click **Resend** 5. To modify before sending: - Select the message - Click **Load** (copies to Send panel) - Modify as needed - Click **Send**

10.6 How to Use Predefined Messages

Goal: Quickly send frequently used diagnostic messages

Steps to send predefined: 1. Go to **Predefined** tab 2. Select a message (e.g., "OBD Engine RPM") 3. Click **Send**

Steps to add your own predefined: 1. In **Send Panel**, set up your message (ID, data, flags) 2. Go to **Predefined** tab 3. Click **Add Current** 4. Your message is now saved for quick access

10.7 How to Monitor Specific ECU Communication

Goal: Analyze communication with a specific ECU (e.g., diagnostic tool ↔ ECU)

Scenario: Monitor diagnostic session with ECU using IDs 0x744 (request) and 0x74C (response)

Steps: 1. Connect to CAN bus 2. Go to **Filters** tab 3. Add filter for requests: - Name: Diag Request - Type: Single - ID: 744 - Accept: ☒ 4. Add filter for responses: - Name: Diag Response - Type: Single - ID: 74C - Accept: ☒ 5. Go to **Main** tab 6. Click ► **Start** to begin receiving 7. Enable **Show ASCII** to see text in data 8. Click **Edit Comments** and add: - ID 744 → Comment: ECU Request - ID 74C → Comment: ECU Response 9. Now you see only diagnostic traffic with clear labels

10.8 How to Export Communication Log

Goal: Save all messages to a file for later analysis

Steps: 1. Capture the messages you want (receive/send) 2. In the toolbar, click **Export TXT** 3. Choose location and filename 4. Click **Save**

The file contains:

| Can0Es - Message Log | | | | | | | | |
|-------------------------------|-----|-------|-----|-------------------------|---------|-------|---------------|--|
| Exported: 2025-12-05 14:30:00 | | | | | | | | |
| ===== | | | | | | | | |
| Time | Dir | ID | DLC | Data | ASCII | Flags | Comment | |
| 12:00:01.123 | TX | 0x744 | 3 | 02 10 01 | ... | | Diag Request | |
| 12:00:01.456 | RX | 0x74C | 8 | 06 50 01 00 19 01 F4 00 | .P..... | | Diag Response | |

10.9 How to Analyze Message Patterns (Grouped View)

Goal: See how often each CAN ID appears and its latest data

Steps: 1. Start receiving messages 2. Go to **Grouped** tab 3. Click **Refresh** to see statistics 4. Table shows: - How many times each ID was received - Last data payload for each ID - Last timestamp 5. Use this to identify: - Most active IDs on the bus - Which IDs have changing vs static data - Missing expected IDs

10.10 How to Switch Themes

Goal: Change between light and dark mode

Steps: 1. Click **Toggle Theme** button (top-left corner) 2. Interface switches between: - **Light:** White background (default, good for bright environments) - **Dark:** Dark background (reduces eye strain in dim lighting)

11. Troubleshooting

Connection Issues

| Problem | Solution |
|---------------------------|--|
| "Cannot load vxlap64.dll" | Install Vector driver package |
| "Channel not found" | Check VN1640A is connected and powered |
| "No license" | Ensure valid Vector license is installed |
| "Access denied" | Close other applications using the channel |

Communication Issues

| Problem | Solution |
|----------------------|--|
| No messages received | Check bus termination (120Ω resistors) |
| TX messages fail | Verify baudrate matches other devices |
| CAN FD not working | Ensure all devices support CAN FD |
| Garbled data | Check baudrate settings on all nodes |

Application Issues

| Problem | Solution |
|--------------------|-------------------------------------|
| GUI freezes | Stop receiving, reduce message rate |
| High memory usage | Clear message list periodically |
| Theme not applying | Restart application |

Appendix A: Keyboard Shortcuts

| Shortcut | Action |
|------------------------------------|---------------------------------|
| <code>Enter</code> (in Send panel) | Send message |
| <code>Ctrl+C</code> | Copy selected messages |
| <code>Delete</code> | Remove selected item (in lists) |

Appendix B: CAN FD Data Lengths

Valid CAN FD payload lengths:

| DLC | Bytes |
|-----|-------|
| 0-8 | 0-8 |
| 9 | 12 |
| 10 | 16 |
| 11 | 20 |
| 12 | 24 |
| 13 | 32 |
| 14 | 48 |
| 15 | 64 |

Appendix C: Common Diagnostic IDs

| ID | Description |
|-------|-------------------------------------|
| 0x7DF | OBD-II functional broadcast address |
| 0x7E0 | OBD-II ECU physical request |

| ID | Description |
|-------------|---|
| 0x7E8 | OBD-II ECU physical response |
| 0x700-0x7FF | Standard diagnostic range |
| 0x744 | Common diagnostic request (vehicle-specific) |
| 0x74C | Common diagnostic response (vehicle-specific) |